



v 1.15  
May 2<sup>nd</sup> 2020

## I. Overview

DCLeap is a Windows application, running in background, to control the movements and events of the mouse and the achievement of specific actions related to the gestures of the hands, all in a virtual reality environment.

**DCLeap is not compatible with Oculus and PiMAX devices.**

### 1) DCLeap software and hardware

DCLeap is composed of :

- Mouse movement management module ;
- Module for managing events linked to the mouse (right and left clicks);
- Module for detecting interactions in the context of hand gestures.

DCLeap was developed in C # with Unity and uses the following solutions :

- Win32 C# mouse ;
- InputSimulatorPlus by TChatzigiannakis ;
- LeapMotion Core SDK for Unity ;
- LeapMotion Interaction engine for Unity ;
- OVR Lay by BenOtter.

The prerequisites of DCLeap are:

- Virtual reality HMD ;
- Headmounted LeapMotion device ;
- DCS World ;
- SteamVR, beta or stable ;
- Drivers CBuchner *driverleap* ([https://github.com/cbuchner1/driver\\_leap](https://github.com/cbuchner1/driver_leap)) ;
- Drivers SDraw *driverleap* ([https://github.com/SDraw/driver\\_leap](https://github.com/SDraw/driver_leap))

### 2) Installation


**Starting from the premise that DCS World, SteamVR and the two "driverleap" are already installed**, unzip the DCLeap.7z archive to the location of your choice. Then, open DCLeap.exe.

Set your settings as desired.

Once filled in, click "Save Settings" button, these settings are stored in Windows registry.

**This registration in the registry is the only entry generated outside the folder in which you unpacked DCLeap.**


These registry keys are under:\Computer\HKEY\_CURRENT\_USER\Software\Leap4DCS\DCLeap



Check the creation of these keys by launching Regedit via the Windows command prompt (Win + R key).

If the keys have been correctly generated and the associated values are correct, run the DCLeap.exe executable.

You should see the Unity window below, make sure the windowed mode is enabled, and then click "Play! ".



Before launching DCLeap, if you're new to LeapMotion and SteamVR, ensure that :

- Leapservice is running
  - o in windows type "services.msc" then scroll down to find *Leap Services*. In not running left click on *Leap Service* line then Start

KtmRm for Distributed Transaction Coordinator	Coordinates transactions between the Distributed Transaction Coordinator (MSDTC) and the Kernel Transac...	Manual (Trigger Start)
Language Experience Service	Provides infrastructure support for deploying and configuring localized Windows resources. This service is ...	Manual
Leap Service		Running
Link-Layer Topology Discovery Mapper	Creates a Network Map, consisting of PC and device topology (connectivity) information, and metadata d...	Automatic
Local Profile Assistant Service	This service provides profile management for subscriber identity modules	Manual (Trigger Start)

- o Your Leap Monitor should show this :



- In the Leap Monitor settings panel that *Allow Images* is checked and in the Tracking settings *Robust Mode* and *Auto-orient Tracking* are both checked too
- SteamVR is running and your LeapMotion is recognized as Steam's controllers




## II. Usage

### 1) Main Menu


When DCLeap is launched, you will access this window, Main Menu, where you can ;

- Define mouse sensitivity ;
- The cursor offset, if you prefer to have the cursor upper, lower more to the left or more to the right;
- Allow hand signals;
- Allow texts popup ;
- Define click method by allowing pinch and/or index trigger gesture;  
*Sometimes, trigger gesture is not identified due to relative position of your hands and the LeapMotion device, that's why **I advise you to check both Pinch and Index to execute clicks.** Indeed, when Trigger is not recognized, I realize the click with a Pinch.*
- Define the sensitivity of the pinch gesture;  
*In other word the distance between your thumb and index, the less it is, more sensitive is the pinch. When Pinch is activated, the cursor is not moving, so if sometimes you try to click on something and your cursor is not moving, this is probably because the pinch is activated. if it happens too often to your liking, maybe try to increase this value*
- Knob neutral position ;  
*To perform a knob rotation, you must execute a pinch gesture, maintain this gesture and then roll to the right or to the left and maintain the position. the more you hold this position in time, the higher the rate will be.  
This cursor will define the neutral position of your wrist, position in which no knob rotation command is sent.*
- Enable the gesture recognitions features.  
*To execute hand signal, you must activate the virtual hand by facing palm.  
For Catapult Shoot and Automatic StartUp, face your right palm, get the green square and then execute the gesture.*



### 2) Help Menu

From this window you can access help reminding the different gestures implanted.



### 3) Start Button


Once you have pressed the Start button, you should see two red and green squares appearing in your VR headset, indicating the activation of the virtual mouse.



Figure 1 – From left to right - both hands move the mouse, only the left hand, only the right

The red square indicates that the mouse control is slave to the left hand, the green square indicates that the control is slaved to the right hand. In order to avoid any disruption related to activation of both hands tracking, it is best to assign mouse tracking to one hand at a time.

DCLeap will tell you when right click is available as shown under (blue square around green/red square).



#### a. Trigger clicks

To execute a trigger click, you need to extend your thumb and your index and after execute trigger gesture. Middle, pinkie and ring can be extended or retracted, it doesn't matter.

#### b. Pinch

Pinch is used to execute standard click and knob rotation. To execute pinch gesture, all fingers can be extended. When you activate pinch, mouse cursor stay in fixed position, then you can rotate your wrist (maintain pinch gesture) as you will be rotating a knob. Sensitivity in accordance with Main Menu set.

#### c. Catapult shoot

DCLeap allow you to execute catapult shoot with the salute gesture. Currently this action is mapped to LSHIFT + LCTRL + S, keybind used by Supercarrier module. **You've to change key mapping in DCS command menu.**

When you execute "Salute" you will see "Catapult Shoot !" in red letters on top right of your HMD (if Allow debug text is ticked in the Main Menu).



#### d. ~~Catapult alignment (deprecated)~~

~~You can align your aircraft to catapult (Keyboard U) with Thumb up gesture. As for catapult shoot, you will see "Catapult Align" in red letters (if Allow debug text is ticked in the Main Menu).~~

#### e. Start-Up

You can execute an automatic start-up procedure by pointing right index finger vertically and gently circling your hand (index must point to the sky for 2 seconds). Mind to map LCTRL + RCTRL + HOME in DCS commands menu.


#### f. ~~Recenter VR view (deprecated)~~

~~You can execute a VR recenter view by closing both fists, palms directions don't matter. Mind to map LSHIFT + RSHIFT + HOME (this can be done by performing fists closed gesture).~~



#### g. Ejection

You can call ejection command by grabbing the handlebar over your head. When your hands will be close the handle, they will be shown in order to help you to grab the handle.  
When grabbed, DCLeap will execute ejection's command.



#### 4) Quit

To exit the application, press the LCTRL + Escape keys. Then click on the "Quit" button in the main menu.

Other, DCLeap automatically quit when SteamVR is shutdown.

#### 5) Debug file

A debug file is generated each time you load DCLeap. Old log is erased before writing a new one.

This file is called Logfile.txt and is contained in the DCLeap\_Data folder.

In case of issue, please attach this file in your post in the DCS forum, or others.

```
2020/05/02_18:24:46
*****
----- System Informations -----
*****
Windows 10 (10.0.0) 64bit | Desktop
NVIDIA GeForce GTX 1080 Ti
Screen_Width : 1920
Screen_Height : 1080
*****
----- Options datas -----
*****
X_Sensitivity : 0,7429544
Y_Sensitivity : 0,7518085
ShowHands : 0
X_Offset : -124
Y_Offset : 19
Debug_Text : 1
Debug_Mouse : 0
Pinch : 1
Index : 1
LeftHandKnob_Neutral : 1,05
RightHandKnob_Neutral : -0,8
PinchActivation_Sensitivity : 0,009939273
CatAlign_HandSignal : 1
CatShoot_HandSignal : 1
Ejection_HandSignal : 1
AutoStart_HandSignal : 1
*****
----- Services Status -----
*****

```


TIME	LeapMotion Status	SteamVR Status	LHand cursor (x;y)	RHand cursor (x;y)
18:24:46	Connected to SteamVR			
18:24:47	LeapMotion service is connected and running	STEAMVR is running	1111;2540	863;2540
18:24:48	LeapMotion service is connected and running	STEAMVR is running	1112;2540	864;2540
18:24:49	LeapMotion service is connected and running	STEAMVR is running	1112;2540	864;2540
18:24:50	LeapMotion service is connected and running	STEAMVR is running	1112;2540	864;2540
18:24:51	LeapMotion service is connected and running	STEAMVR is running	1112;2540	864;2540
18:24:52	LeapMotion service is connected and running	STEAMVR is running	1112;2540	864;2540

*Example of generated  
LogFile*

### III. To go further, or to better understand

#### 1) Pinch gesture

Here is the illustration under Unity of the pinch gesture zone (the red one) and the release pinch zone (the blue one).



#### 2) Palm facing zone

When the white line (line between the HMD and the palm) enter in the red cone, LeapMotion detect your hand is facing your head. Currently the red cone is set at 45°.

